


Settings for VSPE using multiple software with your Perseus. (You don't need com0com using this setup)



1. Open Menu: Create
 - choose Device Connector
 - specify COM 10
 - click button "Fertig stellen"
2. Open Menu: Create
 - choose Device Splitter
 - left window: specify COM 11
 - right window: specify COM 10
 - click button "Fertig stellen"
3. Open Menu: File
 - choose Save as
 - specify a filename xxxx.vspe
4. VSPE do not install a driver on your system.
To run the emulation start the file xxxx.vspe
 - on demand
 - or put it in your folder autostartStart ist before the the Perseus software